

Application: We can apply what we have learned to the (damped) harmonic oscillator

$$m \frac{d^2 y}{dt^2} + b \frac{dy}{dt} + ky = 0.$$

In this case, we are assuming that the parameters m and k are positive and that $b \geq 0$. The characteristic equation $m\lambda^2 + b\lambda + k = 0$ has eigenvalues

$$\frac{-b \pm \sqrt{b^2 - 4mk}}{2m}.$$

There are three cases based on the value of the discriminant $b^2 - 4mk$.

1. $b^2 - 4mk < 0$: In this case, the eigenvalues are complex and can be written as

$$\lambda = \left(-\frac{b}{2m}\right) \pm \left(\frac{\sqrt{4mk - b^2}}{2m}\right) i.$$

The real part determines the exponential decay rate for solutions, and the imaginary part determines the natural “period” of the solutions.

There are two subcases:

- (a) $b = 0$: all solutions are periodic. This is the **undamped** case.
 - (b) $b \neq 0$: solutions oscillate with a constant frequency, but they decay at an exponential rate. This is the **underdamped** case.
2. $b^2 - 4mk = 0$: The eigenvalue

$$\lambda = -\frac{b}{2m}$$

is repeated. This is the **critically damped** case. In this case, solutions approach zero as rapidly as possible.

3. $b^2 - 4mk > 0$: The eigenvalues

$$\lambda = \frac{-b \pm \sqrt{b^2 - 4mk}}{2m}$$

are both real. Note that

$$0 < b^2 - 4mk < b^2.$$

Therefore, both eigenvalues are negative, and the equilibrium point at the origin is a (real) sink. The rate of approach to zero by a typical solution is determined by the “slow” eigenvalue. This is the **overdamped** case.

Example. Consider the one-parameter family of equations

$$\frac{d^2y}{dt^2} + b\frac{dy}{dt} + y = 0.$$

In this case, the characteristic equation is $\lambda^2 + b\lambda + 1 = 0$, and consequently, the eigenvalues are

$$\lambda = \frac{-b \pm \sqrt{b^2 - 4}}{2}.$$

The value $b = 2$ is the critical value for this family.

We can see the progression from underdamped to critically damped to overdamped with a Quicktime animation that I have posted on the web site.

The trace-determinant plane

There is a nice geometric object called the trace-determinant plane that organizes the various types of 2×2 linear systems.

Consider the 2×2 matrix

$$\mathbf{A} = \begin{pmatrix} a & b \\ c & d \end{pmatrix}.$$

Let's calculate the characteristic polynomial of \mathbf{A} :

Conclusion: The eigenvalues of any 2×2 matrix are determined by the trace and the determinant of \mathbf{A} . We have

$$\lambda = \frac{(\text{tr}\mathbf{A}) \pm \sqrt{(\text{tr}\mathbf{A})^2 - 4(\det \mathbf{A})}}{2}.$$


Summary of Phase Portraits

Assume $\det \mathbf{A} \neq 0$. Then zero is not an eigenvalue of \mathbf{A} .

1. Real and distinct eigenvalues
 - (a) sink
 - (b) saddle
 - (c) source
2. Complex eigenvalues
 - (a) spiral sink
 - (b) center
 - (c) spiral source
3. Real and repeated eigenvalues
 - (a) sink with one eigenline in the phase portrait
 - (b) source with one eigenline in the phase portrait
 - (c) sink where every solution is a straight-line solution
 - (d) source where every solution is a straight-line solution

What if $\det \mathbf{A} = 0$?

We can organize these different types using a plane with unusual coordinate axes.



You can turn on the trace-determinant plane in the `LinearPhasePortraits` tool.

Example. Consider the one-parameter family of linear systems

$$\frac{d\mathbf{Y}}{dt} = \begin{pmatrix} -1 & 1 \\ 0 & d \end{pmatrix} \mathbf{Y}.$$

